

LEAD HE HIM TEIN DUM TUAH

Dumthlawhnak i A thabikmi Tuahto ning pawl

- Ei hlan ah thingthei le anhringso pawl kha thiang tein tawl.
- Rawl caah eimi cin tikah, kum 1980 nak in a hlundeuhmi inn pawl i acung in ruah a tlami luannak hrawng kha hrial.
- Vawlei thatnak le cinthlakmi theipar chuahnak thanchoter dingah thinghnah non kha hmang.
- Vawlei tongh in riantuan hnu ah kut kha thiang tein tawl.
- Dumthlawh tikah kuthruk i hruk.
- Inn chung na lut hlan ah na kedan i phoih.

Ngakchia pawl he him tein dum tuah uh – ei mi tisik anhnah dihlak him tein.

Vawlei he dairek in ngakchia pawl tonter kha hrial. Pe pawl, thingthei le anhnah eimi anhringso pawl kha him tein cing hna, asinain ei hlan ah tisik anhnah i ahram kha met hna.

Vawlei he dairek in ngakchia pawl tonter kha hrial. Pe pawl le thingthei anhnah pawl kha him tein cing hna, asinain ei hlan ah ahawng na meh lo ahcun tisik anhnah ahram pawl kha hrial hna.

Hi vawlei ah dairek in dum tuah hlah. A thiangmi vawlei he a sangmi ihkhunh pawl chungah tisik anhnah dihlak cu cing hna.

Lead He Tonnak Ngeihmi kha Zorter!

- Vawlei lead level kha 200 ppm nak in a tamdeuh tik asilole ngakchia pawl he dumthlawh tikah
- A sangmi ihkhunh pawl ser
 - A thiangmi vawlei hmang
 - Dumthlawhnak i A thabikmi Tuahto ning pawl Zul

Lead caah Manlo in Vawlei Hneksaknak

- IUI Center for Urban Health: bit.ly/iui-soil-lead-test or cuh@iu.edu

Man Tlawm Tein Vawlei & Thazaang a pemi Rawl Hneksaknak


- UMass Soil Testing Lab: soiltest.umass.edu/services

Vawlei Lead Ruahkhunnak (ppm)

0 80 200 300 400 500 600 700 800 900 1,000

Laknak ahrampi pawl: Brown, S. L., Chaney, R. L., & Hettiarachchi, G. M. (2016). Lead in urban soils: a real or perceived concern for urban agriculture?. *Journal of environmental quality*, 45(1), 26-36. Kansas State University Agricultural Experiment Station and Cooperative Extension Service, and adopted by the Penn State Cooperative Extension Service. (Assume soil testing for lead with EPA Method 3051A). Filippelli, G. (2002) Garden Safe Garden Well.

LEAD HE HIM TEIN DUM TUAH



Na vawlei hneksaknak kha tuaktaan. Na vawlei tongtham tikah *a thabikmi tuahto ning pawl kha zul. Na inn kha 1978 hlan rak sakmi a si i/asilole hman tukmi lam cungah na um ahcun, na vawlei kha hneksak.

Lead a tammi level hmuh a si. *A thabikmi tuahto ning pawl kha zul. Vawlei lead level, tihnung na inkhawhnak, ngakchia no umnak, le cinmi thingramhnah phung (rawl caah eimi/ei lomi) cungah hngat in a hlankanh in ralrinnak ngei.

*ZAANGFAHNAK IN A THABIKMI TUAHTO NING LEI AH I MER.

